

パソコンの起動はパスワード入力なしにスイッチONだけで良いと思いませんか

パソコンの起動には当然のごとくパスワード入力ですが、そのパソコンを使う場所は殆ど自宅ではありませんか？ 持ち出すのもこの教室くらいで他人に触られる心配が無いのであればパスワード入力を省略する設定で良いでしょう！ チョット心配ならスマホの様に短い数値の PIN コード入力にすることも出来ます。


1. PIN コード設定

①スタート⇒設定








②アカウント⇒サインインオプション

③PIN クリック




④セットアップをクリック



そのアドレスに確認コードが届く。スマホで開いて確認すれば画面閉じることなく行え迷わずに済む

*英数字を含めることも出来るし、4桁以上にすることも出来ますがスマホ同様に4桁が良いでしょう


*パソコン起動時の入力画面でパスワード入力となっている場合は『サインオプション』からPINを選ぶことでPIN入力可能になります



The image shows a Windows Security dialog box titled "PIN のセットアップ" (PIN Setup). It explains that Windows Hello PIN is a secure way to sign in. It contains two input fields: "新しい PIN" (New PIN) and "PIN の確認" (Confirm PIN). Below these is a checkbox labeled "英字と記号を含める" (Include letters and symbols). At the bottom are "OK" and "キャンセル" (Cancel) buttons.

2. パスワード・PIN 入力なしに起動する設定

- ① スタート⇒設定⇒アカウント⇒サインオプション
- ② 『追加の設定』の中にある『セキュリティ向上のため、このデバイスでは Microsoft アカウント様に Windows Hello サインインのみを許可する（推奨）』を OFF にする



The image shows the "追加の設定" (Additional Settings) window. It features a toggle switch for the setting "セキュリティ向上のため、このデバイスでは Microsoft アカウント用に Windows Hello サインインのみを許可する（推奨）" (For security, on this device, only Windows Hello sign-in is permitted for Microsoft accounts (recommended)). The toggle is currently turned off, indicated by a red box around the "オフ" (Off) label. Below this is another setting for "しばらく操作しなかった場合に、もう一度 Windows へのサインインを求めるタイミング" (Timing to request sign-in to Windows after a period of inactivity), which is set to "常にオフ" (Always off).